

Logbook data exchange in RUMlog2Go

You can exchange the complete log database file or you can import and export QSOs via ADIF.

Full log database file exchange

The log databases from the classic and NG versions are not compatible! If you use the NG version on your Mac, you need to use the NG version on your iOS device as well.

An easy way to copy log files is to use the iTunes File Sharing feature. See here for further information: <https://support.apple.com/en-us/HT201301>

If you want to change log files more frequently, you should use Dropbox: <https://www.dropbox.com/home>

If you want to load files on your iOS device, you have to install the Dropbox application: <https://itunes.apple.com/de/app/dropbox/id327630330?mt=8>

Your local files in RUMlog2Go will not be synchronized with the Dropbox, you have to load and save your files always manually.

At the first use, you may be asked for your user name and password by the Dropbox API, the following up- or download will fail. Just try it again.

Load logbook database files from you Mac

Copy the desired file from your Mac to the Dropbox.

iPad: Go to the Log Setting page and press the button „DL from Dropbox“

iPhone: Go to: Settings-->Log settings-->Download file from Dropbox

Navigate to the desired file and confirm the download. **If this file name already exists it will be overwritten without further warnings!** The database is ready to use after selecting it.

Save your logbook database file to the Dropbox

iPad: Go to the Log Setting page and press the button „UL to Dropbox“

iPhone: Go to: Settings-->Log settings-->Upload log file to Dropbox Wait until the upload has finished!

Existing files in the Dropbox will not be overwritten, the file name will be suffixed by a number.

ADIF file exchange

You can exchange ADIF data in simple text or as text file via Dropbox.

Import ADIF file

Copy the ADIF file into your Dropbox.

iPad: Go to the Log Setting page. The lower part is used for an ADIF import.

iPhone: Go to: Settings-->Log Settings-->ADIF Import

Press the „Dropbox“ button to select your ADIF file. The file will be loaded and is shown as text. To import the QSOs press the „Import“ button.

Import ADIF text

Bring the ADIF data as simple text on your iDevice, i.e. use Mail. Mark and copy the whole text into the clipboard.

iPad: Go to the Log Setting page. The lower part is used for an ADIF import.

iPhone: Go to: Settings-->Log Settings-->ADIF Import

Press the „Paste“ button. The text will be pasted into the field. Press the „Import“ button.

Export QSOs in ADIF

Before you can export a QSO, you have to mark the desired QSOs in the log table. A long touch with a single finger toggles the selection of a single QSO row. **A long touch with two fingers in a QSO row will select all following QSOs until the end or until a still selected QSO!**

Press the „Export“ button, which is visible now. You can export your QSOs as:

- Simple ADIF text into the clipboard
- ADIF text file via Mail
- ADIF text file into the Dropbox

Before you can save to the Dropbox, you have to enter a file name.